

DBMaker/DBMaster FAQ Document

Question:

How to use LoadExternalDB to load DB/table/data online?

Answer:

You can use LoadExternalDB to load external DB into local DB directly via DSN.

If set unload external 'connection string', dmSQL will print "set external db 'odbc connection string' " in unload-file.s0 file.

1. unload db1

```
Connect to db1 sysadm;  
  
set unload external 'DSN=db1;UID=SYSADM;PWD=;';  
  
unload db to db1;
```

2. db1.s0 look like

```
...  
  
set external db 'DSN=db1;UID=SYSADM;PWD=;';  
  
create table SYSADM.T1 (  
C1 INTEGER default null ,  
C2 INTEGER default null )  
  
in DEFTABLESPACE lock mode row fillfactor 100 ;  
  
load external db from 'select * from SYSADM.T1' into SYSADM.T1;  
  
...
```

3. load db to destination database:

```
Connect to db2 sysadm;
```

Email: <Support_RD@syscom.com.tw>

DBMaker/DBMaster FAQ Document

Load db from db1; //commit_num is 1000 by default

OR

Load db from db1 100; //commit_num is 100

Note: Please make sure db1 started while loading to db2, and set DB_USRFO=1 in db2 in advance if user FO is used.

Version: 5.4.1

Product: Normal/Bundle

Platform: Windows/Linux